



Supported by



U.S. DEPARTMENT OF
ENERGY

Office of
Science

Solenoid Free Plasma Startup Summary

College W&M
Colorado Sch Mines
Columbia U
Comp-X
General Atomics
INL
Johns Hopkins U
LANL
LLNL
Lodestar
MIT
Nova Photonics
New York U
Old Dominion U
ORNL
PPPL
PSI
Princeton U
Purdue U
SNL
Think Tank, Inc.
UC Davis
UC Irvine
UCLA
UCSD
U Colorado
U Maryland
U Rochester
U Washington
U Wisconsin

R. Raman, D. Mueller, S.C. Jardin
University of Washington/PPPL

This work is supported by US DOE contract numbers FG03-96ER5436, DE-FG02-99ER54519 and DE-AC02-09CH11466

NSTX Research Forum for FY2011-12 Research
March 15-18, 2011
PPPL, Princeton, NJ

Culham Sci Ctr
U St. Andrews
York U
Chubu U
Fukui U
Hiroshima U
Hyogo U
Kyoto U
Kyushu U
Kyushu Tokai U
NIFS
Niigata U
U Tokyo
JAEA
Hebrew U
Ioffe Inst
RRC Kurchatov Inst
TRINITI
KBSI
KAIST
POSTECH
ASIPP
ENEA, Frascati
CEA, Cadarache
IPP, Jülich
IPP, Garching
ASCR, Czech Rep
U Quebec¹

SFPS Research Priorities & Milestone

Research Priorities:

- Minimize reliance on central solenoid flux to achieve 0.8-1MA plasma currents using early NBI/HHFW heating and by reducing impurities
- Assess heating and current drive in inductive low plasma current discharges using HHFW
- Determine maximum achievable closed flux currents with CHI start-up
- Start CHI discharges with a pre-charged central solenoid

Milestones:

R(12-2): Assess confinement, heating, and ramp-up of CHI start-up plasmas

Goals & Objectives for SFPS Research in FY11/12

- Maximum CHI started plasma current
 - Maximum injector current consistent with acceptable low-Z impurities
 - Improvements due to metal electrodes
- Can HHFW increase Te of CHI discharges?
 - Can the current decay time be increased?
- How well does NBI couple to CHI started and ramped discharges?
 - As plasma current varies
 - As density varies
 - NBI power and application time (MHD modes)
 - NBI tangency
- Does early NBI & RF application improve CHI started discharges
- Properties of CHI started discharges vs. normal inductive plasmas
- How much NI current can be driven in low Ip OH and CHI started discharges
- CHI start-up capability needed in NSTX-U for directly coupling to NBI

Proposals Discussed

#	Title	Proposer
1	HHFW heating of OH plasma	Taylor
2	Assess vessel conditions*	Raman
3	CHI-only discharges	Nelson
4	HHFW heating of CHI-only plasmas	Taylor
5	CHI+OH, zero pre-charge	Raman
6	700kA CHI started disc. For ASC	Mueller
7	CHI + pre-charged OH	Mueller
8	High NI current in OH-only plasmas	Taylor
9	NIMROD simulations	Hooper

New Hardware Improvements for FY11/12 Research

- Variable voltage charging capability for the CHI cap bank
 - Should help improve control of absorber arcs
- Higher currents in the PFAB1 and 2 coils
 - For improved absorber arc suppression
- Metal inner divertor plates
 - Reduce low-Z impurities as the injector current is increased
- Dual LITER system
 - Reduce low-Z impurities due to more complete divertor coverage
- Functioning Li-dropper system
 - For improved absorber arc suppression

Run Plan – XP1034, Raman et al., (1 –day in FY11) (obtain time for electrode conditioning time)

- Reproduce FY11 discharges using 4 capacitors
 - To verify machine is able to support higher current discharges
 - This may take more than a day as the CHI electrodes seem to require some time to condition

Run Plan – CHI Only, Nelson et al., (1 to 2 –days in FY11, 1 day in FY12)

- Generate CHI only discharges (No induction) to increase the CHI start-up current level
 - Higher injector currents will be needed as both the capacitor bank size and the injector flux will be increased at $BT=0.55T$
 - The variable voltage capability of the cap bank will be used to adjust the voltage programming to reduce absorber arcs
 - The dual LITERS will be used to reduce low-Z impurities from the injector
 - The PFAB1 and 2 coil current duration and current magnitude will be improved
 - After a limit is reached the upper divertor will be coated with Li using the Li-dropper in an inductive discharge (FY12)
 - In FY12 use boronization & improved vessel conditions to increase I_p
 - Assess current persistence time, electron temperature profile, CHI current locations on divertor plates, spectroscopic lines for reduction on O & C.

Run Plan – CHI Only + RF, Taylor et al., (0.5 to 1 days in FY11, 0.5 to 1 days in FY12)

- Heat the CHI generated discharges (No induction) with HHFW
 - Run after the HHFW XP on heating a low I_p target
 - Use 20-30ms pulses of stable RF at maximum reliable power level (>1 MW)
 - Assess improvements to the electron temperature
 - Assess current persistence time, electron temperature and density profile, changes to O & C lines and compare to No HHFW case

Ramp-up of CHI started discharges with zero pre-charge

Raman et al., (2 days FY11, 4 days FY12)

- Use induction with zero pre-charge to ramp the CHI target to 1MA
 - If improvements are seen with RF application and if RF power is stable use the RF heating pulse and extend the RF pulse duration in these discharges. Otherwise do the initial ramp without RF
 - Initially use similar gas programming as in FY10, then repeat with +/- 50% variation in gas quantity (LFS and CS) to optimize at an improved gas injection level for these higher current discharges
 - Test with SGI (instead of LFS and CS) [FY12]
 - Using NBI at 60keV apply all three sources starting at 40ms & move pulses earlier in time [for TRANSP analysis]
 - Repeat above steps with NBI at 75keV and 90keV [TRANSP analysis]
 - Based on TRANSP results improve the NBI power & timing for FY12
 - Determine lowest density needed to access H-mode (FY12)
 - At the high beam power increase the density to access H-mode

NIMROD & TSC simulations will be used for understanding the detailed reconnection physics and scaling to NSTX-U

TRANSP will be used to determine how best to maximize the NI fraction and to compare confinement properties of discharges with and without CHI

700kA Discharge with Flat-top, Mueller et al., (0.5 to 1.5 days) [May run this in ASC]


- Take a reference discharge from the previous XP that has transitioned to H-mode and limit the maximum I_p to 700kA
 - Use remaining inductive flux to maintain a current flat-top
 - Maintain low density & inductance during flat-top
- Time permitting
 - Transition the discharge to iso-flux control

CHI start-up with pre-charged CS, Mueller et al., (1 to 2 days)

HIT-II routinely operated with fully pre-charged central solenoid

NSTX pre-charged discharges use PF1 & PF3 coils to reduce OH fringing fields and to create a large field null

CHI Started shots: 27517 19 21 23 25
Induction only shots: 27518 20 22 24



Other RF related XPs

- High NI current fraction in low I_p inductive plasmas
 - Taylor (1-1.5 days)
- HHFW ramp-up from 250-400kA
 - Taylor (1-1.5 days)

Overall Run Plan – FY11 (4 to 6 days)

- Taylor (OH+RF) 0.5 – 1 day
- Raman, XP1034 – Assess vessel conditions >1- day
- Nelson (CHI-only) startup 1 day
- Taylor (CHI-only + RF) 0.5 – 1 day
- Raman, (CHI + Zero pre charge OH + RF +NBI) >1 days
 - May need to defer much of this to FY12
- Mueller, CH+OH to 700kA 0.5 to 1 day (in ASC or SFPS)
 - Time permitting or run in ASC

Overall Run Plan – FY12 (5.5 to 7.5 days)

- Taylor (Full non-inductive) 0.5 – 1 day
- Nelson (CHI-only) startup 1 day
- Taylor (CHI-only + RF) 0.5 – 1 day
- Raman, (CHI + Zero pre charge OH + RF +NBI) >3 days
- Mueller, (CHI + pre charged OH) > 2 days
 - Time permitting


SFPS Run Allocation

#	Title	Proposer	Requested Time	Minimum Time Requested	Total Allocation	FY-11 1st	FY-11 2nd	FY-12 1st	FY-12 2nd	3rd
1	HHFW heating of OH plasma	Taylor	1.5	1	0.5	0.5	0	0	0	0
2	Assess vessel conditions*	Raman	1.5	1	1	1	0	0	0	0
3	CHI-only discharges	Nelson	4	2	2	1	0	0.75	0.25	0
4	HHFW heating of CHI-only plasmas	Taylor	1.5	1	1	0.5	0	0.25	0.25	0
5	CHI+OH, zero pre-charge	Raman	6	4	4	0	1	3	0	0
6	700kA CHI started disc. For ASC	Mueller	1.5	0.5	0	0	0	0	0	1
7	CHI + pre-charged OH	Mueller	3	1	0	0	0	0	0	1
8	High NI current in OH-only plasmas	Taylor	1.5	1	1	0	0	0.5	0.5	0
9	NIMROD simulations	Hooper	10	0	0	0	0	0	0	0
					0	0	0	0	0	0
		TOTALS:	27.5	11.5	9.5	3	1	4.5	1	2

*Request CHI Electrode conditioning time (1 day) similar to the time given to RF for antenna conditioning

FY-11 Total:	4	9.5 Allocation
FY-12 Total:	5.5	
TOTAL:	9.5	

Milestone related XPs: XPs shown in Yellow Boxes to be run during same run-campaign



SFPS XPs Prioritized to Meet Milestones and Support Required Information for NSTX-U

Significant Improvements in CHI startup capability for SFPS Research

2008: Transitioning to an H-mode

2009: CS flux savings

2010: Low inductance & density (needed for NSTX-U Advanced Scenarios)

- Maximum CHI started plasma current
 - Maximum injector current consistent with acceptable low-Z impurities
 - Improvements due to metal electrodes
- Can HHFW increase T_e of CHI discharges?
 - Can the current decay time be increased?
- How well does NBI couple to CHI started and ramped discharges?
 - As plasma current varies
 - As density varies
 - NBI power and application time (MHD, fast ion modes)
 - NBI tangency
- Does early application of NBI & RF improve CHI started discharges?
- Properties of CHI started discharges vs. normal inductive plasmas
- How much NI current can be driven in low current OH and CHI started discharges?
- How much CHI start-up capability is needed in NSTX-U for directly coupling to NBI?

Run Plan (CHI + OH, zero pre-charge)

- Equilibrium control
 - Adjust the PF1, 2 and 3 coil currents in the pre-programmed phase to improve the equilibrium control and reduce the I_p dip usually seen around 30ms (reduce plasma wall contact)
 - Adjust the PF5 preprogrammed current for these higher current discharges to improve equilibrium during the feedback controlled phase
 - Assess improvements over FY10 results
- Assess confinement improvement (FY12)
 - Using the improved vessel conditions further improve the initial CHI start-up current magnitude as it should now be possible to operate at higher injector currents
 - Based on the methods developed in FY11, re-establish ramp-up using induction and appropriate NBI and RF conditions
 - Assess confinement, heating and ramp-up of CHI started plasmas
 - Repeat reference discharges with No RF
 - Repeat reference discharges with No NBI (but short NBI for MSE)

Run Plan (CHI + OH, zero pre-charge)

- Analysis
 - In discharges with and without NBI and with NBI time variations use TRANSP analysis to determine & compare to OH-only discharges
 - thermal confinement (& for discharge with and without RF)
 - NBI coupling efficiency & NI current fraction
 - With electron density
 - With IP
 - Beam power
 - Beam tangency
 - Use magnetics & q-profile evolution to determine evolution in internal inductance and elongation of CHI started and non-CHI started discharges
 - Assess MHD modes in CHI started and reference OH-only discharges
 - Low and high densities cases for stable operation
 - In low density L-mode and higher density H-mode

CH+OH, Zero pre-charge

- Assess benefits of metal cathode
 - Compare to discharges in FY10 to determine lower divertor oxygen and carbon intensities with injector current
 - Improvements to maximum injector current consistent with acceptable low-Z impurity levels
 - Possible metal influx into long-pulse discharge
 - Repeat discharges after a recent boronization to assess benefits of covering larger area of vessel with boron (to further reduce carbon and oxygen)

NIMROD & TSC simulations will be used for understanding the detailed reconnection physics and scaling to NSTX-U

TRANSP will be used to determine how best to maximize the NI fraction and to compare confinement properties of discharges with and without CHI

CHI start-up with pre-charged CS, Mueller et al., (1 to 2 days)

- Restore inductive discharge No. 120406 (OH at 4kV, No PF2, No PF1B – DN, 3 NBI sources).
 - Increase BT to 0.55T and repeat
 - Reduce the pre-charge in CS to +2.5kA (10% of nominal value), self consistently reduce the other coil current
- Now add in the CHI injector waveforms as follows:
 - Superimpose CHI injector coil currents from a recent shot
 - Current pre-programming in PF3s may not needed for CHI start-up
 - Improve after running a vacuum calculation using LRDFIT
- If there is difficulty in attaining a breakdown, increase current in PF1A in steps to reduce fringing field from the OH
 - After successful discharge initiation and ramp-up, increase the magnitude of the pre-charge in 10% increments
 - Use the CHI voltage and gas programming from a recent CHI started discharge